

VACUUM SOLUTIONS FROM A SINGLE SOURCE

Pfeiffer Vacuum stands for innovative and custom vacuum solutions worldwide, technological perfection, competent advice and reliable service.

COMPLETE RANGE OF PRODUCTS

From a single component to complex systems: We are the only supplier of vacuum technology that provides a complete product portfolio.

COMPETENCE IN THEORY AND PRACTICE

Benefit from our know-how and our portfolio of training opportunities! We support you with your plant layout and provide first-class on-site service worldwide.



ASM Pocket is a free application to transform a smartphone or tablet into a wireless remote control for ASM leak detectors.

With ASM Pocket you can control the following leak detector functions:

- Indication of leak rate and pressure with measured value and bargraph display
- Line graph/progression chart display
- Vacuum and sniffing modes available
- Start/stop of a test cycle
- Autocalibration
- Zero function

You can download ASM Pocket from the Apple App Store and Google Play Store:

Google Play Store



Apple App Store



Are you looking for a perfect vacuum solution?
Please contact us:

Pfeiffer Vacuum GmbH
Headquarters · Germany
T +49 6441 802-0

(PL 0015 P EN April 2017/5)

ASM POCKET

www.pfeiffer-vacuum.com

Quick start guide

PFEIFFER  VACUUM

PFEIFFER  VACUUM

ASM POCKET

Requirements to operate ASM Pocket:

- Leak detector – the following versions of ASM leak detectors will work with ASM Pocket: ASM 310, ASM 340 series and ASM 380
- Older models such as ASM 182 series or ASM 192 series require software version v3100 or higher and 5 V output available on the RS-232 connector (5 V output on RS-232 can be switched on the interface board. Please contact your local service point for support)
- Smartphone or tablet, based on iOS 8.1 or Android 4.0.3 or higher
- External dongle to allow communication between leak detector and smartphone or tablet



Bluetooth dongle (only for Android devices):

If you are already using the RC 500 WL wireless remote control, you can use the provided dongle (radio transmitter).

If you don't have the RC 500 WL, please order:



Description	Order number
Bluetooth dongle	PT 445 422
Adapter cable ASM/dongle to connect the dongle to the leak detector	A466613




WiFi dongle (for Android and iOS)

This set includes the dongle, its antenna and the cable to connect to the RS-232 port of the leak detector




Description	Order number
WiFi dongle	125902



Starting ASM Pocket with Bluetooth (only Android):

- Ensure the "serial link1" for RS-232 on the leak detector is set to "advanced mode"
- Connect the Bluetooth dongle to the RS-232 port of the leak detector
- Switch on the dongle
- Make sure Bluetooth is turned on on your smartphone or tablet
- Open the ASM Pocket app
- A list of available Bluetooth devices will be displayed
- Choose the correct one (refer to the name on the dongle according to the leak detector you want to communicate with)

Note: If a password is requested, it is either 1234 or 0000 (optionally 5555)




Smartphone

Tablet

Starting ASM Pocket with WiFi (Android and iOS):

- Ensure the "serial link1" for RS-232 on the leak detector is set to "advanced mode"
- Connect the WiFi dongle to the RS-232 port of the leak detector
- Make sure WiFi is activated on your smartphone or tablet
- Go to the WiFi settings
- Select "Pfeiffer-Vacuum" network
- Enter "PfeifferASM" as password
- Open the ASM Pocket app
- Go to "Settings"
- Enter the IP address and communication port of the WiFi dongle (refer to sticker at the back of the dongle)
- Make sure Telnet is not used

Note: When using iOS, ignore messages that WiFi is not activated. If you are connected to the Pfeiffer-Vacuum network, you will be able to communicate.



ASM Pocket help center

For online technical support, there is a dedicated website for additional information and trouble shooting: <https://asmocket.zendesk.com>

ASM Pocket is a free app and only basic functions are available. If you would like to use more complex functions, please order the remote control for ASM leak detectors from Pfeiffer Vacuum.